

HTML

ECMAScript

SMIL

CSS

Installing and Using NetFront v3.3 for S60



INSTALLATION

Before you start the installation make sure you have at least 2-3 Mb free memory on your phone.

➔ **If NetFront is already installed, it is recommended to first uninstall the existing version using "Tools/Manager". Existing bookmarks will not be deleted.**

Start the infrared or Bluetooth client application on your computer and send the SIS (Symbian installation) file to the phone. It will arrive as a message on your phone. Go to Inbox and select the message containing the installation file. The file will be automatically saved to the installer application. Select Install and press [OK]. Read the agreement and if you accept, press [OK]. If you do not accept the agreement, press [Cancel], and the installation will be aborted.

➔ **If you receive an "out-of-memory" message during installation, delete the installation file from your inbox after it has been copied to the installer. Go to "Tools/Manager" and install NetFront manually.**

GOING ONLINE

Configuring your Internet Access Point

For browsing with NetFront you need to define an Internet access point on your phone which is different from existing WAP or MMS access points. This is done in the phone's main menu / tools / settings / connection settings. Usually a phone comes with a number of access points predefined for several providers. Otherwise the Nokia Setting Wizard application coming preinstalled on many phones can configure your access points automatically. If all of this doesn't work, ask your provider for the Internet settings, and you also will find a list of operator's settings on our website

www.access-sys-eu.com/accesspoints.html.

Getting started

After the installation you will find the NetFront icon in the phone's main menu. When you start NetFront for the first time you are asked whether you want to add some links to the bookmarks. Bookmarks include NetFront web page, frequently asked questions and company pages. Those bookmarks will not be removed automatically when you uninstall NetFront from your phone.

Opening a Web page

NetFront provides several ways to open a page: From the bookmark list, by entering a URL, or open a list of previously entered URLs, go to previous or next page, use the history list, or by opening pages that have been saved to the phone's local drive.

NAVIGATING WITH NETFRONT

Navigating within pages

Normal navigation within a web page is done by using the cursor control. Using the arrow keys in any direction moves the focus to the next link/image in that direction. The focus on anchors is highlighted. You can hold down an arrow key for fast scrolling. Scrolling speed can be controlled in the browser settings.

Selecting items

To select an item on a web page or in a menu, navigate to the respective item by using the cursor control. When you arrive at the item - usually it will be highlighted by a rectangular frame or some background color - activate it by pressing the selection key.

USING NETFRONT

Menus

Pressing [OPTIONS] takes you to the main menu of NetFront which is the control center of the application. Here you have access to all settings, commands and options. More efficient than using the menu is to make use of the *keypad shortcuts*.

View modes

Switch to Full screen mode to use the entire screen for displaying web pages. Toggle between different page rendering modes by using the "#" shortcut: Desktop setting displays the site without any screen optimization; Smart-Fit optimizes pages for the small screen, and Text-Only mode NetFront drops images to reduce memory consumption and transmitted data thus saving cost.

Saving images and pages

With the predefined shortcut "7" or from the Tools menu you can activate Save image mode. Scroll the page and select the image that you would like to save and press the selection key, then the left softkey. The image is saved into your phone's photo album. Pressing back will bring you back to normal browsing mode. The Save page command saves the whole page including images into a single file that you can later read offline from the "Saved pages" folder.

New window

You can have up to four browser windows open at the same time. Use the Open/New window command to add one and the Next window command to switch to the next open window of your browsing session.

Bookmarks

Pressing shortcut "6" takes you to the bookmark list. Select a page and press the cursor control to open one. To add the currently opened web page to the bookmark list press shortcut "3". If a title is defined in the web page this information will be added, too. To edit this title, or manage your bookmarks, open the bookmarks list, navigate to the desired bookmark and press [OPTIONS] *Edit*.

Search and find

Find in the page lets you search for an occurrence of a search string in a page. To continue the search select *Find next* or press "9". To scan the Internet for certain information with Google search choose *Find on the Web*.

Shortcuts

Shortcuts provide quick access to certain browser functionality. The browser comes with the following shortcuts predefined:

- 1 (Go to) Top of page
- 2 (Go to) Bottom of page
- 3 Add bookmark
- 4 Open URL
- 5 Entered URLs
- 6 Bookmarks
- 7 Save image
- 8 Next window
- 9 Find next
- 0 NetFront settings
- * Full screen on/off
- # Change rendering mode

The "for Symbian OS" logo means the product has been successfully tested in Symbian Signed. For more information visit www.symbiansigned.com.

Copyright © 2005 ACCESS CO., LTD. All rights reserved. NetFront is a trademark of ACCESS CO., LTD. in Japan and selected countries worldwide. ACCESS is a registered trademark of ACCESS CO., LTD. in Japan. Symbian and the "for Symbian OS logo" are trademarks or registered trademarks of Symbian Software Ltd. The trademarks, logos and trade names stated in this document are the property of other third parties.



ACCESS Systems Europe GmbH
Essener Str. 5/ TZU-IV
D-46047 Oberhausen, Germany
phone: +49-208-8290-6464
nf3support@access-sys-eu.com